<u>Command Reference</u> > <u>SCPI Command Reference</u> > <u>MMEMory Commands</u> > MMEMory:STORe:CORRection

MMEMory:STORe:CORRection <Channel>, <CalGroupFile>

Copies the correction data of channel <Channel > to the cal pool, generating a new correction data file (cal group). The file has the extension *.cal and is stored in the C:\Users\Public\Documents\Rohde-Schwarz\Vna\Calibration\Data directory.

Setting parameters:

<Channel> Channel number

<CalGroupFile> String parameter to specify the name of the created cal group file.

There is no need to specify the directory path and file extension;

the analyzer uses the default cal pool directory

C:\Users\Public\Documents\Rohde-

Schwarz\Vna\Calibration\Data and a *.cal extension.

Example: See MMEMory:LOAD:CORRection

Usage: Setting only

Manual operation: See "Add / Add All / Replace / Apply / Apply to All"

Top